


EDITOR






STEP 4




In the Clipeditor you have listened to all recorded files and noticed that Test03.mp2 has a very long introductory pause, that is not needed to publish.

Position the cursor over Test 03. mp2 and choose menu Tools → Editor *. You can now mark the beginning and end of this file.

You now see the Test03.mp2 recording in the Edit window. Here you can both play and record. As well as this, you also have the option of viewing the recording's volume trace. When using this function it is easy to visually establish where the beginning and end markers should be placed approximately. As well as this, you can use the fast-forward and rewind buttons to move quickly through the recording while hearing fragments of it. This gives the possibility of aurally assessing where the important parts of the recording are located.

- Choose Edit → Crop Begin or Edit → Crop End. You define the absolute begin and end of the recording. The actual recording before the begin or after the end is not gone, only the begin and end positions are marked and used in the clip-editor or during publishing. Notice that 2 counters are presented in the screen, the left one is the current position of the cursor, the right one is the total length of the clip-list which is updated each time you make any changes to the clip you're editing.
- If you have set markers during the recording, they are shown at their position in the upper part of the volume trace. You can also define new markers with the menu item Edit/Mark.

To remove markers set the cursor on the marker and press the red arrow . You can also undo  or redo  this.

- The  and  buttons are used to jump to markers in one go. If, for example, you are at the beginning of the file and you have set markers at 1/4 and then 3/4 of the recording, then the  key will bring you immediately to 1/4, then to 3/4 and then to the end of the recording. If you then press that key again you will jump to the beginning of the following clip in the clip-list, etc.

If, after playing, you press Stop and then for a second time press Stop again, the cursor will jump back to where you started playing before.

- If you want to use or save a piece of the recording to a new file you can also use Edit/Crop Begin and Edit/Crop End to select the range you want to copy. Choose File → Save selection and that part is now saved to a file ready to be added to any Clip-list. If you open Clip Editor and choose insert file you can add the piece of recording in to the list.

** If you use 'Luci Edit' you have extra features added to the ones mentioned. See the Luci Edit Manual for more information.*