


N>TRANS



START SETUP IN YOUR PROGRAMS FOLDER

Select page N>Trans

This tab will appear when Luci detects the N>Trans.

EXPLANATORY FIELDS AND BUTTONS

Input jack

Choose the input you will use.

Mic Bias

Switch on the Mic Bias here.

AGC

Set the Automatic gain control.

Input sensitivity

Mic +20dB: Microphone-input with 20dB extra gain

Mic: for Microphone-input

Line: for Line level input

Limiter On

This is an analog limiter for the microphone-signal, that can be used to prevent nasty digital overloading.

The gain-level and headphone-output-level can be controlled from within Luci.

Go to adjust the next page or press OK to save and leave Setup.